



# MOTION RECORDING SETUP


Written By: Q-See EP



## **INTRODUCTION**


**BY DEFAULT, YOUR SYSTEM IS SET FOR 24/7 MOTION DETECTION RECORDING.**

## Step 1 — MOTION RECORDING SETUP




- Click **Start** in the Menu Bar

## Step 2




- Click **Settings**

## Step 3




- Click **Motion** in the Camera tile.


## Step 4




- Select the **Camera** you wish to enable.
- Click **Motion** and select **ON**.
- ⓘ *Repeat for any other cameras you wish to enable for motion.*


## Step 5




 **To modify the regions of the camera for motion detection:**

- Refer to the **Example** to see how to add/remove regions.
- **Click and Drag** the mouse in the camera view to make changes.
-  *Repeat for any other cameras you wish to enable for motion.*


## Step 6



 **Once you have configured all of your cameras:**

- Click **Apply**


## Step 7



 To enable Motion Recording and configure the schedule:


- Click **Record** in the top menu bar.

## Step 8




- Select **Motion Record** as the Record Mode.

## Step 9




- Advanced camera settings can be modified if required.
- The default settings are optimized for the highest quality recording and streaming for your recorder. Changes to these settings should not be made unless you are an expert user, or were advised by a Q-See agent.
- Click OK

## Step 10




- Click **Apply**

## Step 11



- Click **Schedule Config**


## Step 12



- ★ To modify the schedule for **ALL** cameras:
- Click **Motion Record Schedule** and Select **Edit**.




## Step 13



- Click **All** to fill the schedule.


**i** Clicking **All** will set your system to 24/7 motion recording. The following steps will show you how to refine the schedule.

## Step 14




- Click the Trashcan to remove specific times.
- **Click and Drag** the mouse to make changes.

## Step 15




- Once completed, click **OK**

## Step 16



- ★ **To modify the schedule for a specific camera:**
  - Click the **Modify** icon for the desired camera.
- ⓘ *Follow the same process shown in Steps 13 thru 15 to make changes to cameras individually.*

## Step 17



- Click **Apply**

## Step 18



- ★ **Once motion is detected by a camera:**
  - A **Motion**, instant, messenger icon indicator will appear next to the recording indicator.
- ⓘ **Once motion is no longer detected, you will only see the recording indicator during post record.**